

## Ardour 3 Monitor modes

monitoring mode	Tape Machine Mode	Track Rec Enable	Master Rec Enable	Transport	Auto Input	Meter	Monitor
Ardour	No	No	No	Stop	On	Input	Input
Ardour	No	No	No	Stop	Off	Track (silence)	Track (silence)
Ardour	No	No	No	Play	On	Track (Audio)	Track (Audio)
Ardour	No	No	No	Play	Off	Track (Audio)	Track (Audio)
Ardour	No	No	Yes	Stop	On	Input	Input
Ardour	No	No	Yes	Stop	Off	Track (silence)	Track (silence)
Ardour	No	No	Yes	Play	On	Track (Audio)	Track (Audio)
Ardour	No	No	Yes	Play	Off	Track (Audio)	Track (Audio)
Ardour	No	Yes	No	Stop	On	Input	Input
Ardour	No	Yes	No	Stop	Off	Input	Input
Ardour	No	Yes	No	Play	On	Input	Track (Audio)
Ardour	No	Yes	No	Play	Off	Input	Input
Ardour	No	Yes	Yes	Stop	On	Input	Input
Ardour	No	Yes	Yes	Stop	Off	Input	Input
Ardour	No	Yes	Yes	Play	On	Input	Input
Ardour	No	Yes	Yes	Play	Off	Input	Input
Ardour	Yes	No	No	Stop	On	Track (silence)	Track (silence)
Ardour	Yes	No	No	Stop	Off	Track (silence)	Track (silence)
Ardour	Yes	No	No	Play	On	Track (Audio)	Track (Audio)
Ardour	Yes	No	No	Play	Off	Track (Audio)	Track (Audio)
Ardour	Yes	No	Yes	Stop	On	Track (silence)	Track (silence)
Ardour	Yes	No	Yes	Stop	Off	Track (silence)	Track (silence)
Ardour	Yes	No	Yes	Play	On	Track (Audio)	Track (Audio)
Ardour	Yes	No	Yes	Play	Off	Track (Audio)	Track (Audio)
Ardour	Yes	Yes	No	Stop	On	Input	Input
Ardour	Yes	Yes	No	Stop	Off	Input	Input
Ardour	Yes	Yes	No	Play	On	Input	Track (Audio)
Ardour	Yes	Yes	No	Play	Off	Input	Input
Ardour	Yes	Yes	Yes	Stop	On	Input	Input
Ardour	Yes	Yes	Yes	Stop	Off	Input	Input
Ardour	Yes	Yes	Yes	Play	On	Input	Input
Ardour	Yes	Yes	Yes	Play	Off	Input	Input
Audio Hardware	No	No	No	Stop	On	Input	Silence
Audio Hardware	No	No	No	Stop	Off	Track (silence)	Track (silence)
Audio Hardware	No	No	No	Play	On	Track (Audio)	Track (Audio)
Audio Hardware	No	No	No	Play	Off	Track (Audio)	Track (Audio)
Audio Hardware	No	No	Yes	Stop	On	Input	Silence
Audio Hardware	No	No	Yes	Stop	Off	Track (silence)	Track (silence)
Audio Hardware	No	No	Yes	Play	On	Track (Audio)	Track (Audio)
Audio Hardware	No	No	Yes	Play	Off	Track (Audio)	Track (Audio)
Audio Hardware	No	Yes	No	Stop	On	Input	Silence
Audio Hardware	No	Yes	No	Stop	Off	Input	Silence
Audio Hardware	No	Yes	No	Play	On	Input	Track (Audio)
Audio Hardware	No	Yes	No	Play	Off	Input	Silence
Audio Hardware	No	Yes	Yes	Stop	On	Input	Silence
Audio Hardware	No	Yes	Yes	Stop	Off	Input	Silence
Audio Hardware	No	Yes	Yes	Play	On	Input	Silence
Audio Hardware	No	Yes	Yes	Play	Off	Input	Silence
Audio Hardware	Yes	No	No	Stop	On	Track (silence)	Track (silence)
Audio Hardware	Yes	No	No	Stop	Off	Track (silence)	Track (silence)
Audio Hardware	Yes	No	No	Play	On	Track (Audio)	Track (Audio)
Audio Hardware	Yes	No	No	Play	Off	Track (Audio)	Track (Audio)
Audio Hardware	Yes	No	Yes	Stop	On	Track (silence)	Track (silence)
Audio Hardware	Yes	No	Yes	Stop	Off	Track (silence)	Track (silence)
Audio Hardware	Yes	No	Yes	Play	On	Track (Audio)	Track (Audio)
Audio Hardware	Yes	No	Yes	Play	Off	Track (Audio)	Track (Audio)
Audio Hardware	Yes	Yes	No	Stop	On	Input	Silence
Audio Hardware	Yes	Yes	No	Stop	Off	Input	Silence
Audio Hardware	Yes	Yes	No	Play	On	Input	Track (Audio)
Audio Hardware	Yes	Yes	No	Play	Off	Input	Silence
Audio Hardware	Yes	Yes	Yes	Stop	On	Input	Silence
Audio Hardware	Yes	Yes	Yes	Stop	Off	Input	Silence
Audio Hardware	Yes	Yes	Yes	Play	On	Input	Silence
Audio Hardware	Yes	Yes	Yes	Play	Off	Input	Silence